

* Copyright (c) 2024, Leopard Imaging Inc. All Rights Reserved.


Overview

This firmware is for LI-USB30-VENUS-OX03D4C-GM2A camera.

This firmware supports 1928 x 1536 @ 30 fps.

This camera doesn't include ISP and outputs 10-bit raw data.

Platform	Camera
1 x LI-GMSL2-USB	1 x LI-VENUS-OX03D4C-GM2A
Cable	Adapter/Carrier Board
1 x USB 3.0 Micro-B cable	1 x 12VDC power supply
1 x FAK-SMZSMZ Fakra cable	





Revision	SVN version	Release Date	Author	Tested By	
2024_05_08		05/08/2024		Shelby Hache	
Updates					
Revision		Description		Release Date	
2024_05_08	First Release			05/08/2024	
Known bugs					



Setup Procedure 1/3

- Hardware:

- 1. LI-VENUS-OX03D4C-GM2A Camera x 1
- 2. LI-GMSL2-USB Tester x 1
- 3. FAK-SMZSMZ Fakra cable x 1
- 4. USB 3.0 Micro-B cable x 1
- 5. LI-PS12-01 x 1

- Hardware Setup:

Connect the camera and USB 3.0 Tester board as the picture on the first page.

- Software:

This camera kit can be tested with any one of the below software:

1. Camera tool (Windows OS)

The Camera tool can be downloaded from the link below: https://www.dropbox.com/s/8daqfypyhnubjr5/CameraUSB30 3 2 20190622.7z?dl=0

It's better to use the 7-zip to uncompress the package:

http://www.7-zip.org/download.html

And install the software below on your PC:

https://www.dropbox.com/s/6uswl40z8rqh2et/vcredist_x86.exe?dl=0

If needed, you can also download the camera tool SDK:

https://www.dropbox.com/s/j6ccl8cvt75gu2g/USB30 CameraTool SDK rev1440 20190622.7z?dl=0

2. Linux Camera tool (Linux OS)

The Linux camera tool can be downloaded from link below.

https://www.dropbox.com/s/4m2efo696px9739/linux camera tool-master 20190624.zip?dl=0

For how to install it, please refer to the README.md in below link. (the latest version of Linux camera tool may have an issue, so please use above Linux camera tool)

https://github.com/LI01/linux_camera_tool

Please follow the README.md in GitHub to install the Linux camera tool.

There are instructions online for how to install the OpenCV on Ubuntu OS.

Below is an example:

https://www.learnopencv.com/install-opencv-3-4-4-on-ubuntu-18-04/

Run Camera 1/3


- Camera Tool (Windows OS)

- 1. Connect the camera to port J1 of USB 3.0 Tester. (refer to picture in page 1)
- 2. Plug in the 12V power supply to USB 3.0 Tester.
- 3. Connect the camera to your PC (USB3.0 port) using the USB 3.0 cable.
- 4. Open camera Tool.

Please make sure to complete these steps in numerical order. Steps 2 and 3 cannot be reversed.


Color matrix:

You can adjust the color matrix in Options → Configuration. Below is an example:



Register access function:

This camera supports register access function. The IC2 Address is 0x6C



	Exposure Setting	Gain Setting
Reg Addr	0x3501	0x350a
Reg Value	0x <mark>0</mark> 1	0x <mark>0</mark> 1


Change the highlighted value to adjust the levels.

You can also use BatchCmd.txt file to write/read register.

Run Camera 2/3


Capture Image:

The images can be captured by clicking Options \rightarrow CaptureImage. Two images (RAW and BMP) will be saved to PC.



The raw image can be viewed by ImageJ.

https://www.dropbox.com/s/fsvfmdy6s9ft03i/ImageJ.7z?dl=0





This camera tool supports Raw-to-RGB function



Note: This camera tool supports Raw-to-RGB function which will reduce the display frame rate. You can click Options → DisableDisplay to get actual frame rate from the sensor. You can also use other regular software (like AMcap) to get higher frame rate, but the video will be green (like below) due to lack of Raw-to-RGB conversion function.



Run Camera 3/3


- Camera Tool (Linux OS)

- 1. Connect the camera to J1 of USB 3.0 Tester. (refer to picture in page 1)
- 2. Plug in the 12V power supply to USB 3.0 Tester.
- 3. Connect the camera to PC (USB3.0 port) through USB 3.0 cable.
- 4. Open a terminal and use the command "leopard cam" to open the camera.

Please make sure to complete these steps in numerical order. Steps 2 and 3 cannot be reversed.

Set the camera as below to get better image quality. Camera Control File Help Device: Leopard Imaging - LI-OX03D4C Firmware Rev: 2048 Sensor Datatype: O RAW10 O RAW12 O YUYV O RAW8 Raw Camera Pixel Format: O BGGR O GBBR O RGGB O GRBG O MONO ☑ Enable auto white balance ☐ Enable auto brightness&contrast ☐ Enable auto exposure Exposure: Gain: ☐ Just sensor read/write I2C Addr: 0x Register Addr Width: 0 8-bit 0 16-bit ○ 8-bit ○ 16-bit Register Value Width: Reg Addr: Read Reg Value: 0x Write Capture: Capture bmp Capture raw Gamma Correction: Apply □ Enable Trigger Sensor: Shot 1 Trigger 0 Black Level Correction: Apply

This camera tool can be used to write/read registers and capture Raw and BMP images.





Note 1/3

This camera kit is pre-loaded with Firmware (in USB 3.0 Tester) and FPGA (in USB 3.0 Tester). If there are any new firmware and/or FPGA binary from Leopard Imaging, you can refer to below instructions to update them.

1. Firmware Update:

Please use the LP_USB3_FirmwareUpdateTool in the camera tool folder to update the firmware.

- 1) Click "Erase" to erase the old firmware.
- 2) Click "FW Update" button to select the lif file. (If the "FW_Update is unavailable, please install the WestBridge driver, check below)
- 3) The update process may take about 15 seconds.
- 4) If the process takes too long, please disconnect the USB and reconnect it to PC. Then try the update tool again.

——Install WestBridge:

If the camera cannot be recognized after you update the firmware, and there is a device name "WestBridge" on the Device Manager, please download the driver from the link below and install it.

https://www.dropbox.com/s/4yx2p31b7qo2gjx/WestBridge_driver.zip?dl=0

- 1) Right click on "WestBridge" and select Update Driver Software.
- 2) Choose browse my computer for driver software.
- 3) Click Browse, locate the driver at the downloaded and unzipped folder. (C:\temp\driver\bin\ for example) If your PC has Win7 or later version, please select the folder "win7".
- 4) Click next and complete the installation process.

After install the driver, please update the firmware again.

Note 2/3

2. FPGA Update:

FPGA Binary: Radar_USB3_top_top_Radar_USB3_top_top.rbt


1) Download the Lattice programmer tool software **Programmer Standalone 3.10 64-bit for Windows** from link below and install it to your PC.

http://www.latticesemi.com/programmer

2) Connect the HW-USBN-2A or HW-USBN-2B to J2 of LI-MAX9296-DESER board. Below is the pinout. You may need to build an adapter cable for the programmer tool and J2. J2 is a 1.27mm pitch interface. Below pins in red need to be connected.

Only below pins in red need to be connected:


TI954 Board <> HW-USBN-2B	TI954 Board <> HW-USBN-2B
Pin1: V_3.3V <> VCC	Pin2: SCK_D19 <> TCK/SCLK
Pin3: N/A	Pin4: SDO_D18 <> TDO/SO
Pin5: N/A	Pin6: SPI_CS_N <> ISPEN/PROG
Pin7: GND <> GND	Pin8: SDI_D20 <> TDI/SI
Pin9: N/A	Pin10: CRESET_B <> TRST





Note 3/3

- 3) Connect the USB3.0 Tester to your PC via USB 3.0 cable.
- 4) Open LP_USB3_FirmwareUpdateTool in the camera tool folder and click "Erase" to erase the firmware.
- 5) Open Lattice software (which you installed in 1). The Device name should be "LIF-MD6000". Set the settings of "Operation" as below and click "OK".



8) Refer to the "Firmware Update" section to install the firmware.

Output Tcl Console